

## **Potentially Hazardous Biological Agents Risk Assessment**

### **Use this information to complete PHBA Risk Assessment Form (6A)**

Use this information to complete PHBA Risk Assessment Form 6A

Risk assessment defines the potential level of harm, injury or disease to plants, animals and humans that may occur when working with biological agents. The end result of a risk assessment is the assignment of a biosafety level which then determines the laboratory facilities, equipment, training, and supervision required.

Risk assessment involves:

- Assignment of the biological agent to a risk group
- Studies involving a known microorganism must begin with an initial assignment of the microorganism to a biosafety level risk group based on information available through a literature search.
- The study of unknown microorganisms and the use of fresh tissues relies on the expertise of the supervising adult(s).
- Determination of the level of biological containment available to the student researcher to conduct the experimentation. (See “Levels of Biological Containment” for details.)
- Assessment of the experience and expertise of the adult(s) supervising the student.
- Assignment of a biosafety level for the study based on risk group of biological agent, level of biological containment available and the expertise of the Qualified Scientist or Designated Supervisor who will be supervising the project.
- If a study is conducted at a non-regulated site (e.g. school), the biosafety level must be confirmed by the local or affiliated fair SRC. If the research is conducted at a Regulated Research Institution, the biosafety level must be assigned by an Institutional Biosafety Committee (IBC) or equivalent approval body or a letter from an institutional representative certifying that the research does not require review. If no approval body exists at the Regulated Research Institution, a letter or document from the Regulated Research Institution that the research does not require review is required and the local or affiliated fair SRC must review the project and assign a biosafety level. If possible, this review should be before experimentation.

### **Classification of Biological Agents**

#### **Risk Groups**

Biological agents, plant or animal, are classified according to biosafety level risk groups. These classifications presume ordinary circumstances in the research laboratory, or growth of agents in small volumes for diagnostic and experimental purposes.

BSL-1 risk group contains biological agents that pose low risk to personnel and the environment. These agents are highly unlikely to cause disease in healthy laboratory workers, animals or plants. The agents require Biosafety Level 1 containment. Examples of BSL-1 organisms are: *Escherichia coli* strain K12, *Agrobacterium tumifaciens*, *Micrococcus leuteus*, *Neurospora crassa*, *Bacillus subtilis*.

BSL-2 risk group contains biological agents that pose moderate risk to personnel and the environment. If exposure occurs in a laboratory situation, the risk of spread is limited and it rarely would cause infection that would lead to serious disease. Effective treatment and preventive measures are available in the event that an infection occurs. The agents require Biosafety Level 2 containment. Examples of BSL-2 organisms are: *Mycobacterium*, *Streptococcus pneumonia*, *Salmonella choleraesuis*.

BSL-3 risk group contains biological agents that usually cause serious disease (human, animal or plant) or that can result in serious economic consequences. Projects in the BSL-3 group are prohibited.

BSL-4 risk group contains biological agents that usually produce very serious disease (human, animal or plant) that is often untreatable. Projects in the BSL-4 group are prohibited.

### **Levels of Biological Containment**

There are four levels of biological containment (Biosafety Level 1–4). Each level has guidelines for laboratory facilities, safety equipment and laboratory practices and techniques.

BSL-1 containment is normally found in water-testing laboratories, in high schools, and in colleges teaching introductory microbiology classes. Work is done on an open bench or in a fume hood. Standard microbiological practices are used when working in the laboratory. Decontamination can be achieved by treating with chemical disinfectants or by steam autoclaving. Lab coats are required and gloves recommended. The laboratory work is supervised by an individual with general training in microbiology or a related science.

BSL-2 containment is designed to maximize safety when working with agents of moderate risk to humans and the environment. Access to the laboratory is restricted. Biological safety cabinets (Class 2, type A, BSC) must be available. An autoclave should be readily available for decontaminating waste materials. Lab coats, gloves and face protection are required. The laboratory work must be supervised by a scientist who understands the risk associated with working with the agents involved.

BSL-3 containment is required for infectious agents that may cause serious or potentially lethal diseases as a result of exposure by inhalation. Projects in the BSL-3 group are prohibited.

BSL-4 containment is required for dangerous/exotic agents that pose high risk of life-threatening disease. Projects in the BSL-4 group are prohibited.